

Create a sensor activity notification

A sensor activity notification notifies recipients when a sensor is opened or activated.

To create a sensor activity notification using the website:

1. Log into the website.
2. Click **Notifications**.
3. Click **+ New Notification**.
4. Click **Sensor Activity**.
5. Name the new notification rule.
6. In *When any of these sensors are open or activated*, click to select the sensors to monitor.
 - If you do not see the sensor you want to monitor, verify monitoring is enabled for it.
7. In *During this time frame*, select either:
 - **At All Times** to receive a notification every time the selected sensors are opened or activated.
 - **Only During the Following Times** to specify a specific time to receive notifications when the selected sensors are opened or activated.
8. In *Notification Filtering*, click to select any desired notification filtering settings.
9. Click **+ Add Recipient**.
10. In the *Address book*, click to select the recipients to notify, or click **+ New** to add a new *Address Book* recipient.
11. Click **Close**.
12. Verify the notification is configured with the correct settings.
13. Click **Save**.

To create a sensor activity notification using the app:

Note: If you do not see the options, verify the app is on the most updated version.

1. Log into the app.
2. Tap Menu.
3. Tap **Notifications**.
4. Tap **+**.
5. In *Create Your Own*, tap **Sensor Activity**.
6. Name the new notification rule.
7. In *When any of these sensors are open or activated*, tap to select the sensors to be monitored.
8. In *During this time frame*, tap to select either:
 - **At All Times** to receive a notification every time the selected sensors are opened or activated.
 - **Only During the Following Times** to specify a specific time to receive notifications when the selected sensors are opened or activated.
9. In *Notification Filtering*, tap to select any desired notification filtering settings.
10. Tap **+ Add Recipients**.
11. In the *Address book*, tap to select the recipients to notify, or tap **+ Add Contact** to add a new *Address Book* recipient.
12. Tap **Close**.
13. Verify the notification is configured with the correct settings.
14. Tap **Save**.